

139. UNQUENTUM IODI DENIGRESCENS.

Stainless Iodine Ointment.

Iodine	1 ounce	10 Gm.
Soft Paraffin	19 ounces	190 Gm.

Finely powder the Iodine ; heat the Paraffin until liquefied, then add the Powdered Iodine, continuing a gentle heat, and stirring until fully combined, then remove from heat and stir until it congeals.

140. UNQUENTUM EMPLASTRI PLUMBI.

Ointment of Lead Plaster.

Diachylon Ointment.

Lead Plaster	1 ounce	110 Gm.
Soft Paraffin	1 ounce	110 Gm.
Oil of Bergamot	4 minims.	1 Cc.

Melt the Lead Plaster and Paraffin together ; when the mixture approaches the temperature of 160° or 170° F., add the Oil and stir until it congeals.

141. UNQUENTUM PHENOLIS CAMPHORATUM.

Camphorated Phenol Ointment.

Phenol	15 parts
Camphor	30 parts
Hydrous Wool-Fat	60 parts
Yellow Beeswax	40 parts
Yellow Soft Paraffin	300 parts

Liquify the Paraffin, Beeswax and Wool-Fat, by the aid of a gentle heat, and while the mixture is still warm, dissolve in it the Phenol and Camphor, and stir until it congeals.

142. UNQUENTUM RESORCINI COMPOSITUM.

Compound Resorcin Ointment.

(N.F. 1906)

Resorcin	1 ounce	85 grains	60 Gm.
Zinc Oxide	1 ounce	85 grains	60 Gm.
Bismuth Subnitrate	1 ounce	85 grains	60 Gm.
Oil of Cade	2 3/8 fluidounces		120 Cc.
White Paraffin Ointment	7 ounces		350 Gm.
Hydrous Wool-Fat	7 ounces		350 Gm.

Triturate the Resorcin to a fine powder with the aid of a little Ether, and allow the Ether to evaporate ; then mix the powders and incorporate with the remainder of the ingredients.

NOTE.—Darkens on exposure to air and light, and should be kept in tightly covered containers.